

la marzocco technical bulletin #171

GB5 X-S Firmware 1.0.0-RC4

July 23, 2021

La Marzocco has released updated firmware, version 1.0.0-RC4, for the new GB5 X-S.

Below is a list of changes:

- Flowmeter test: this feature has been introduced in the factory menu.
- Water probe: water values are now displayed as TDS and (estimated) Total Hardness.
- Doses programming: long-press time to access doses programming on each button has change from 2 to 3 seconds, to avoid accidental overwriting.
- Pre-infusion: if enabled, it is now also activated while programming doses.
- Pulses: max value has been increased to 9999.

The new firmware can be found [here](#). If the link is not working for you, please copy and paste the following link into your web browser of choice:

https://lamarzoccousa.com/wp-content/uploads/2021/07/gb5_s-x_1.0.0-RC4.zip

Do not hesitate to contact our solutions team with any questions you have about this technical bulletin.

solutions.usa@lamarzocco.com

206.706.9104 x101